



Release Notes

Version: 4.2.0.2

Release Date: 1/31/2022

Maintenance Release:

- **AccessDME Bug Fixes**
 - Fixed issue with Export/Copy window not exporting CSV containing hash values.
 - Fixed issue with Export/Copy window not retaining destination path.
 - Fixed issue with Item Inventory being greyed out by default.
 - Fixed issue with Save Layout crashing if Tree View was selected in Items window.

Version: 4.2.0.1

Release Date: 1/12/2022

New and Improved Features:

- **QuickView LT™ Video Player**
 - Now supports audio-only files, such as WAV and MP3, and displays audio in Waveform or Spectrograph view in QuickView LT.
 - Added a button to toggle audio waveform view when viewing a video with audio.
 - QuickView LT now includes file information header when pasting from different files into the same QuickView LT notes window.
 - QuickView LT HTML notes window now displays page margins and scales images to stay within margins.

Version: 4.1.1.0

Release Date: 11/01/2021

New and Improved Features:

- **QuickDME™ QuickView in AccessDME™**

- QuickDME Note Taking Capability – This new feature allows notes to be taken while reviewing video within AccessDME or when viewing video outside of AccessDME, Notes can be easily saved to a PDF file.
- **QuickView LT™ Video Player**
 - QuickView LT Standalone Installer - This 17MB installer allows anyone to use the Free QuickView LT MM Video Player accessible from Windows Explore > Right click context menu. Download it today.
 - QuickView LT archive-R™ Integration – You can now play videos and sequence previews prior to archiving from within archive-R.
 - QuickView LT Zoom Controls were added allowing you to display video at preset zoom levels.

Version: 4.1.0.0

Release Date: 02/01/2021

New and Improved Features:

- **QuickView LT™ Video Player** now available via Windows right-click context menu to play all FFmpeg supported video files, including many proprietary containers w/standard streams!
 - Integrated w/Omnivore FFmpeg Convert. With a single click, users can send video from the free QuickView video player to Omnivore’s FFmpeg Convert for further interrogation & processing.
 - New **Metadata Viewer** displays file metadata reported by MediaInfo, ExifTool & FFprobe in a single tabbed window, as well as a summary report comparing all three. Users can quickly copy and/or save any or all of these reports!
 - Added ability to copy frame to clipboard.
 - Added ability to right-click and copy any metadata text field displayed in the player to clipboard (*e.g. duration, timecode, pkt_position, pict_type*)
- **Synology NAS Integration** introduced! Whether you’re looking for a complete turnkey digital asset management solution OR want to leverage an existing Synology NAS, QuickDME’s database & storage can be setup & deployed on a single, expandable NAS!
- **AccessDME:**
 - Added ability to add Notes to individual items & integrated all notes (*e.g. Case, Download, Item notes*) in a new tab within the items window.
 - Added ability to add text-only comments on any file via Items List View.
 - Added ability to view and/or encode video with Macroblock & motion vector information displayed.
 - Added option to automatically start Derivative ingest after Send-To FFmpeg tasks.
 - Grouped default FFmpeg Send-To options under right-click context menu. (*User Requested*)
 - Added new folder type for derivative “Supporting Data”. Users can append data inside a Supporting Data folder.
 - Improved image redaction feature & related derivative process.

- Added Windows right-click context menu option to quickly verify hash values for content copied out of AccessDME.
- Added ability to sort Items Window by column titles.
- Added new **“Transfer Log” report** to reports menu w/detail on source & server hash, etc. *(User Requested)*
- Added new **“Hash” report** to reports menu, providing easy way to export Download CSV containing original source & server hashes. *(User Requested)*
- Added ability to Copy Text displayed for items in List View to clipboard *(User Requested)*
- Reformatted Metadata panel to improve legibility.
- Added row shading for Items List view to improve legibility *(User requested)*
- Downloader:
 - Extended multiple case download feature to allow multiple ingests for a single case *(User Requested)*
 - **Create Local Copy** on Ingest w/global & override permissions, including ability for each user to set local folder preference, complete with cryptographic hashes.
- Admin Config:
 - Archive & Restore feature upgraded to 64-bit, can now archive up to petabytes of data.
 - Added **“Custom Search”** capability in Purge Tab. *(User Requested)*

Bug Fixes:

- Fixed issue with Disc Burning that prevented users from being able to create more than 1 disc.
- AccessDME: Fixed issue with audio playback not working when AccessDME window is resized so small all player controls aren't able to be displayed.
- AccessDME: Fixed issue with purging from Case level that occasionally produced an error.
- AccessDME: Fixed issue preventing users from typing in Personnel ID field when moving items.
- AccessDME: Fixed issue with changing an existing case's Case #.
- AccessDME: Fixed issue w/some TIFF images only displaying thumbnails.
- AccessDME: Fixed thumbnail selection issue.
- AccessDME: Fixed issue with saving interface layout.
- Downloader: Fixed issue preventing notification to user that their network is **“Offline”**.